

# Eddyfi Magnifi® GO 5.0R5 Release Notes

Release date: September 6, 2022

## **\*\*\*Cloud-based licensing system\*\*\***

Magnifi 5.0 is now activated through a cloud-based licensing system.

For clients under a valid maintenance plan, access to version 5.0 is included and preactivated. After installing the new version, simply connect the instrument to the internet to activate the license.

If you are not under a valid maintenance plan, please contact your Eddyfi Technologies sales representative.

## Resolved Issues

- Unexpected recurring error message for perpetual licenses with expired maintenance plan are removed.

## Known Issues, Limitations, and Restrictions

### Surface Applications (GO)

- Ability to select behaviour for *Next / Previous Indication* button (Detected, Reported or All) was added for the desktop version of Magnifi but is missing in Magnifi GO.

### Generic

- Data List naming format always returns to Free Format when loading an inspection sub-folder.
- Some files from the Documentation section of the backstage have not been updated.
- The unit of some fields has changed from samples (smpl) to counts (cnt).
- Magnifi can take a few seconds to close.

## System Requirements

- Eddyfi Reddy for surface (32/32M, 64/64M or 128/128M)
- Eddyfi Reddy for tubing (AC-E)

## Firmware

- 2.1R7 (included in MagnifiGO installer package)